



# READ ME FIRST

## Microsoft SQL Server Installation Instructions

---

### **STS SQL Server Software Installation**

This document provides installation instructions for a network version of STS. The database used is Microsoft SQL Server™.

Setup the SQL database:

1. Set Server Authentication to SQL Server and Windows Authentication Mode.
2. Use SQL Server Management Studio to create a new database called "winsts".
3. Create a new Security Login name called "sts\_user" (all lower case letters), using SQL Server authentication, with a password of "grump" (all lower case letters). Make sure to uncheck all check boxes relating to passwords. Set the default database to winsts. Before saving, continue to the next step.
4. Under User Mapping, check the winsts database, and set database role memberships of db\_datareader and db\_datawriter. Click OK to save the login.
5. Using the File menu Open >> File - Load the "winsts.sql" file from the CD, select the "winsts" database, and execute the script to create the database tables. Then open the "winsts\_data.sql" file, select "winsts" database, and execute the script file.

To install STS:

1. Copy files from the STS CD to a common folder on the server.
2. Double-click to modify the "winsts.ini" file in notepad. In the [Settings] section, change the ProdServer= line to access your server (example: ProdServer=myserver2). If you are using a named instance, add it with a backslash (example: ProdServer=myserver2\SQLEXPRESS). In the [Connect] section, set Type=SQLSERVER and Provider=SQLOLEDB.
3. Run "setup\_pc.exe", located in the common folder on the server, from each user computer.
4. Start the application by double-clicking on the desktop Stores Tracking System icon.
5. The system automatically defaults to a "DEMO" registration. Purchasers must enter the **Customer Ident** code and the **License Key** provided by GigaTrak with your CD, and click the Register button.
6. Proceed to the "Quick Start Information" guide.